

# TRANSPORT PRO

**Split Dispatch** 



# **Table of Contents**

Split Dispatches in Transport Pro	
Add a Split Dispatch/Team Drivers	




#### **Split Dispatches in Transport Pro**


Transport Pro accommodates unique dispatch scenarios. For example, if you need to split the pay on a load because one driver is taking the load from point A to point B, and another driver is taking that same load from point B to point C, you can do this by setting up a **split dispatch**. This scenario may also be referred to as dispatching **team drivers**. In addition, sometimes customers wish to receive one invoice, even though the move requires two trucks. The system can create two separate dispatch records to represent each movement. This is handled from the Load Summary screen. This document assumes that you have already added your load information, including any stopoffs.

### Add a Split Dispatch/Team Drivers

1. Navigate to the Load for which you need to enter a split dispatch/team drivers. You will want to make sure you are on the Load Summary screen.



2. Scroll down to the Dispatch History section and click "+Add Dispatch."






3. An Edit Dispatch window will open. Enter the information for driver A. If Driver A is dropping the load off so that driver B can pick it up, you need to check the "Drop this trailer?" box.

Be sure to select the correct origin and destination in the Dispatch Information section by checking the correct boxes. In the screen shot below, you can see that the origin is Dickson, the stopoff is Birmingham and the consignee is Doral. In this example, driver A is going to take the load from Dickson to Birmingham, and when he gets to Birmingham, he is going to drop the trailer.

To split the payment for the load between the drivers on the load, we highly recommend flat rating them. If you normally pay a percentage of freight, we recommend figuring out what that percentage is and entering it as a flat rate. For example, let's say you normally pay each driver on the load 75 percent of the line haul, but in this scenario, you need to split that 75 percent between two drivers, which means that each driver on the load would actually be getting paid 37.5 percent of the freight. While you can change the percentage on the dispatch to represent this, we have found that flat rating just tends to be easier, especially if you have more than two dispatches/drivers on the load.

You **MUST** insert dates in the yellow fields as well. Once everything looks correct on the dispatch, click "Save."



## TRANSPORT PRO

4. You will now see the first leg of the dispatch in the Dispatch History section. Now, you need to add the second leg of the dispatch for driver B. To do this click on the "+Add Dispatch" link.




**NOTE**: In this scenario you will notice a warning message in a yellow bar in the Dispatch History section. This will appear after you enter the first dispatch. This is because on the first leg of the dispatch you only have the origin and stopoff check marked. This warning message is here to alert you that you still need to move the load from the stopoff to the consignee. Once you add your second leg with driver B, this warning message will disappear.





5. An Edit Dispatch window will open. Enter the information for driver B. The system should have automatically checked the correct locations for you in the Dispatch History section. In this case, the load is going from the stopoff to the consignee. Again, we highly recommend that you flat rate the driver just as you did with driver A. All yellow fields are required.



Now you will see both legs of the dispatch in the Dispatch History section.

Dispatch Histo	ory					
Last Updated	Dispatch	Driver / Broker Carrier	Tractor	Trailer	Freight Bill	P
Transport Pro Administrator 12/29/2016	1842	Reed, John	1032	1019	Tractor - 750 Flat Org Contract Rate - 80%	
Transport Pro Administrator 12/29/2016	1841	Reed, Jim	1028	1020	Tractor - 750 Flat Org Contract Rate - 75%	

**NOTE**: Again, we recommend paying split loads via a flat rate method. Paying a flat rate gives users flexibility to split the freight and fuel earnings between trucks as needed. If you need to pay on a percentage or per-mile basis, the system will divide not only the freight, but additional items/accessorials such as fuel, detention, etc. by the number of dispatches on the load. For example, if you do pay per mile or by a percentage and have two dispatches on the load, the system will divide the **TOTAL** amount by two.